Interference: ray and wave pictures

 Interference results from the sum of two waves with different phase:

$$E_{tot}\left(\Delta\phi\right) = E_1 e^{ikz} + E_2 e^{ikz + \Delta\phi}$$

We measure intensity, which leads to interference

$$I_{tot} (\Delta \phi) \propto \left| E_1 e^{ikz} + E_2 e^{ikz + \Delta \phi} \right|^2 = \left| E_1 + E_2 e^{i\Delta \phi} \right|^2$$
$$= I_1 + I_2 + \sqrt{I_1 I_2} e^{i\Delta \phi} + \sqrt{I_1 I_2} e^{-i\Delta \phi}$$
$$= I_1 + I_2 + 2\sqrt{I_1 I_2} \cos(\Delta \phi)$$


- For the case where $I_1 = I_2$,

$$I_{tot}(\Delta\phi) = 2I(1 + \cos(\Delta\phi)) = 4I\cos^2(\Delta\phi/2)$$

• How to generate, calculate phase difference?


The Fizeau Wedge Interferometer

The Fizeau wedge yields a complex pattern of variable-width fringes, but it can be used to measure the wavelength of a laser beam.




Fizeau wedge calculation


Interference between reflections from internal surfaces



- Angle is very small, neglect change in direction
- Path difference: $\Delta l = 2L \sin \alpha \approx 2L \alpha$
- Phase difference: $\Delta \phi = \frac{\omega}{c} n \Delta l \approx 2\pi \frac{2L}{\lambda} \alpha$ n = 1
- Interference: $I_{tot}(\Delta \phi) = I_1 + I_2 + 2\sqrt{I_1I_2}\cos(\Delta \phi)$
- One fringe from one max to the next, so maxima are at $\Delta \phi = 2\pi m$
- In this interferometer, minimum path = 0, we can measure absolute wavelength: $\Delta \phi = 2\pi m = 2\pi \frac{2L}{\lambda} \alpha \rightarrow \lambda = \frac{2L}{m} \alpha$


Newton's Rings






Newton's Rings

Get constructive interference when an integral number of half wavelengths occur between the two surfaces (that is, when an integral number of full wavelengths occur between the path of the transmitted beam and the twice reflected beam).



Tilted window: ray propagation

- Calculate phase shift caused by the insertion of the window into an interferometer.
- Ray optics:
 - Add up optical path for each segment
 - Subtract optical path w/o window



Tilted window: wave propagation


Write expression for tilted plane wave

$$E(x,z) = E_0 \exp\left[i\left(k_x x + k_z z\right)\right] = E_0 \exp\left[i\frac{\omega}{c}n\left(x\sin\theta_2 + z\cos\theta_2\right)\right]$$

Snell's Law: phase across surfaces is conserved

 $k_{x}x = \frac{\omega}{c}n\sin\theta \qquad \text{is constant}$ $\Delta\phi = (k_{2}\cos\theta_{2})L_{w} - (k_{1}\cos\theta_{1})L_{w}$


 This approach can be used to calculate phase of prism pairs and grating pairs




Multiple-beam interference: The Fabry-Perot Interferometer or Etalon

A Fabry-Perot interferometer is a pair of **parallel** surfaces that reflect beams back and forth. An etalon is a type of Fabry-Perot etalon, and is a piece of glass with parallel sides.

The transmitted wave is an infinite series of multiply reflected beams.



Multiple-beam interference: general formulation



r, t = reflection, transmission coefficients from air to glassr', t' = ""from glass to air

δ = round-trip phase delay inside medium = k₀(2 n L cos θ_t)


Transmitted wave:

$$E_{0t} = tt' e^{-i\delta/2} E_0 \left(1 + (r')^2 e^{i\delta} + ((r')^2 e^{i\delta})^2 + ((r')^2 e^{i\delta})^3 + \dots \right)$$

Reflected wave:

$$E_{0r} = rE_0 + tt'r'e^{i\delta}E_0 + tt'r'(((r')^2 e^{i\delta})^2 E_0 + \dots$$

Stokes Relations for reflection and transmission



Notes:

- relations apply to angles connected by Snell's Law
- true for any polarization, but not TIR
- convention for which interface experiences a sign change can vary


$$\begin{aligned} \textbf{Fabry-Perot transmission} & \text{Stokes'} \quad r' = -r \\ \text{relations} \quad r'^2 = r^2 \\ \text{The transmitted wave field is:} \\ E_{0r} = tt' e^{i\delta/2} E_0 \Big(1 + (r')^2 e^{i\delta} + ((r')^2 e^{i\delta})^2 + ((r')^2 e^{i\delta})^3 + ... \Big) \\ = tt' e^{i\delta/2} E_0 \Big(1 + r^2 e^{i\delta} + (r^2 e^{i\delta})^2 + (r^2 e^{i\delta})^3 + ... \Big) \\ \Rightarrow \quad E_{0r} = tt' E_0 / (1 - r^2 e^{-i\delta}) \\ \text{Where:} \\ \text{Power transmittance:} \quad T \equiv \left| \frac{E_{0r}}{E_0} \right|^2 = \left| \frac{tt' e^{i\delta/2}}{1 - r^2 e^{i\delta}} \right|^2 = \frac{(tt')^2}{(1 - r^2 e^{+i\delta})(1 - r^2 e^{-i\delta})} \\ = \left[\frac{(tt')^2}{(1 + r^4 - 2r^2 \cos(\delta))} \right] = \left[\frac{(1 - r^2)^2}{(1 + r^4 - 2r^2 [1 - 2\sin^2(\delta/2)])} \right] = \left[\frac{(1 - r^2)^2}{(1 - 2r^2 + r^4 + 4r^2 \sin^2(\delta/2)]} \right] \\ \text{Dividing numerator and denominator by } (1 - r^2)^2 \\ \qquad \qquad T = \frac{1}{1 + F \sin^2(\delta/2)} \quad \text{where:} \quad F = \left[\frac{2r}{(1 - r^2)} \right]^2 \end{aligned}$$

Multiple-beam interference: simple limits


Reflected waves

$$T = \frac{1}{1 + F\sin^2\left(\delta / 2\right)}$$

Full transmission: $sin() = 0, d = 2 \pi m$




Minimum transmission: sin() = 1, d = 2 π (m+1/2)



Constructive interference for reflected wave


Etalon transmittance vs. thickness, wavelength, or angle π 1



- The transmittance varies significantly with thickness or wavelength.
- We can also vary the incidence angle, which also affects δ .
- As the reflectance of each surface (R=r²) approaches 1, the widths of the high-transmission regions become very narrow.

The Etalon Free Spectral Range

The Free Spectral Range is the wavelength range between transmission maxima.



1/(round trip time)

Etalon Linewidth

The Linewidth δ_{LW} is a transmittance peak's full-width-half-max (FWHM).

$$T = \frac{1}{1 + F \sin^2\left(\delta / 2\right)}$$

A maximum is where $\delta/2 \approx m\pi + \delta'/2$ and $\sin^2(\delta/2) \approx \delta'/2$

Under these conditions (near resonance),

$$T = \frac{1}{1 + F\delta'^2 / 4}$$


This is a Lorentzian profile, with FWHM at:

$$\frac{F}{4} \left(\frac{\delta_{LW}}{2} \right)^2 = 1 \quad \Rightarrow \quad \delta_{LW} \approx 4 / \sqrt{F}$$

This transmission linewidth corresponds to the minimum resolvable wavelength.

Etalon Finesse

The Finesse, \Im , is the ratio of the Free Spectral Range and the Linewidth:



Using: $F = \left[\frac{2r}{1}\right]^2$


$$\Im = \frac{\pi}{1 - r^2} \qquad \text{taking } r \approx 1$$


The Finesse is the number of wavelengths the interferometer can resolve.

Multilayer coatings

Typical laser mirrors and camera lenses use many layers.


The reflectance and transmittance can be custom designed






Quarter-wave stack

Multilayer thin-films: wave/matrix treatment




- Use boundary conditions to relate fields at the boundaries
- Phase shifts connect fields just after I to fields just before II
- Express this relation as a transfer matrix
- Multiply matrices for multiple layers

High-reflector design



Reflectivity can reach > 99.99% at a specific wavelength > 99.5% for over 250nm Bandwidth and reflectivity are better for "S" polarization.

Interference filter design



A thin layer is sandwiched between two high reflector coatings -very large free spectral range, high finesse

- typically 5-10nm bandwidth, available throughout UV to IR